


Technical Service Bulletin

March 25, 2024

CD14 - Version 2.03 Software Release

The software has been updated to include bug fixes and improvements as listed below.

Release Type			
Maintenance		Major	Critical

Software Information	
New Version	V2.03
Previous Version	V2.02

Serial Number (Change will be effective in units before the serial numbers listed below.)	
Black	244-135-1100
Sliver	744-135-1100

Release Notes
<ul style="list-style-type: none">● Resolves random playback stopping with some discs.● Minor bug fixes.

For more information or questions please contact your customer service representative.

-- End --

Technical Service Bulletin

November 27, 2023

CD14 - Version 2.02 Software Release

The software has been updated to include bug fixes and improvements as listed below.

Release Type		
Maintenance	Major	Critical

Software Information	
New Version	V2.02
Previous Version	V2.01

Serial Number (Change will be effective in units before the serial numbers listed below.)	
Black	244-135-1100
Sliver	744-135-1100

Release Notes
<ul style="list-style-type: none"> • Optimized MCU communication scheme to eliminate unexpected playback stops. • Fixed a bug where the total remaining time in Program mode is incorrect. • Minor bug fixes and improvements.

For more information or questions please contact your customer service representative.

-- End --

Technical Service Bulletin

July 10, 2023

CD14 - Version 2.01 Software Release

The software has been updated to include bug fixes and improvements as listed below.

Release Type			
Maintenance		Major	Critical

Software Information	
New Version	V2.01
Previous Version	V1.32

Serial Number (Change will be effective in units before the serial numbers listed below.)	
Black	244-135-1100
Silver	744-135-1100

Release Notes
<ul style="list-style-type: none"> ● Fixed a bug where sometimes unexpected playback stop occurred when the CD player played disc in REPEAT ALL mode. ● Improved the PAUSE mode to automatically enter STOP mode after 5 minute to extend the life of CD mechanism. ● Other minor bug fixes.

For more information or questions please contact your customer service representative.

-- End --



Technical Service Bulletin

October 12, 2020

CD14 - Version 1.32 Software Release

The CD14 software has been updated including bug fixes and improvements as listed below.

Release Type		
Maintenance	Major	Critical

Software Information	
New Version	V1.32
Previous Version	V1.31

Serial Number (Change will be effective in units start from the serial numbers listed below.)	
Black	244-024-1001
Silver	744-024-1001

Release Notes
<ul style="list-style-type: none">Fixed a bug where CD-Text was not updated when playing a CD without manually changing tracks.

For more information or questions please contact your customer service representative.

-- End --

Technical Service Bulletin - Updated

Mar 28, 2019

CD14 - Version 1.31 Software Release

The CD14 software has been updated to Version 1.31. This release includes power consumption regulations. Release details are listed below.

Release Type		
Maintenance	Major	Critical

Software Information	
New Version	V1.31
Previous Version	V1.27

Serial Number (Change will be effective in units starting with the serial numbers listed below.)	
Black	244-825-1001
Silver	744-836-1001

Release Notes
<ul style="list-style-type: none"> Changed the default value of OFF TIMER from DISABLE to 20 MINS to meet the power consumption regulations. <i>Note that unit would enter STANDBY mode when the following conditions are fulfilled:</i> <ol style="list-style-type: none"> Unit is in STOP state. (Pressing STOP key twice) No RS232 or ROTEL LINK communication No actions from remote control or front panel keys Added OFF TIMER warning message display. Unit will display a blinking remaining-time message three times in the last three minutes, each for 5 seconds, and will display a static warning message in the last ten second.

For more information or questions please contact your customer service representative.

-- End --

Technical Service Bulletin

November 27, 2023

CD14 - Version 2.02 Software Release

The software has been updated to include bug fixes and improvements as listed below.

Release Type		
Maintenance	Major	Critical

Software Information	
New Version	V2.02
Previous Version	V2.01

Serial Number (Change will be effective in units before the serial numbers listed below.)	
Black	244-135-1100
Sliver	744-135-1100

Release Notes
<ul style="list-style-type: none"> • Optimized MCU communication scheme to eliminate unexpected playback stops. • Fixed a bug where the total remaining time in Program mode is incorrect. • Minor bug fixes and improvements.

For more information or questions please contact your customer service representative.

-- End --



Technical Information

DATE: October 25, 2016

MODEL: CD14

Software Release Notes

The following document contains details of the software updates for the CD14.

Key:

New Feature

Feature Change

Bug Fix – Critical

Bug Fix – Minor

Main Software

V1.24 to V1.27

October 25, 2016

- **Bug Fix (Minor):** Fixed an issue where user set dimmer settings could be reset after a power cycle.
- **Bug Fix (Minor):** Fixed an intermittent bug where the display would show track names from the previous disc played when a new CD was first inserted.

V1.22 to V1.24

September 19, 2016

- **Bug Fix (Minor):** Fixed an intermittent bug where the display would remain displaying "EJECT" until the play button is pushed.
- **Bug Fix (Minor):** Improved error correction when playing scratched CDs.